


TDM Ports and Protocols



TDM Client – Uses TCP ports 80 or 443 (HTTPS) both ways to connect to the server. WorkBench also uses TCP port 24007 to connect directly with an 860 DSPi in the field, and TCP port 1433 to connect to the shared TDM database.

TDM Server – Uses TCP ports 80 or 443 to connect directly with WorkBench. For meter connection, the server uses TCP port 24007 to connect to the meter to send its data (outbox) information to the 860 DSPi.

860 DSPi – The 860 DSPi uses TDP port 80 to connect and send its data to the TDM server. The 860 DSPi can use TCP port 443 to connect to the server to send data using SSL encryption.

Mail Server – If using mail server ports TCP 25 (SMTP) or 465 (SSMTP) and 110 (POP3) or 995 (SSL-POP) these ports need to be opened both ways.

For Additional Help Contact
 Trilithic Applications Engineering
 1-800-344-2412 or 317-895-3600
support@trilithic.com or
www.trilithic.com

TDM Ports and Protocols
 P/N 0010275055 – Rev 01/10
 1 of 1